

SmartCollision™ SDK

API Reference

Version 2.01

January 12, 2007



3D Incorporated

3D Incorporated LICENSE AGREEMENT



1. Software

As used herein, the term, “Software” means the software accompanying this Agreement, including: (i) the object code form of 3D Incorporated’s library of function calls and the ASCII form of 3D Incorporated’s header files for function calls (the “API”); and (ii) the executable form of certain 3D Incorporated’s software tools (“Tools”).

2. Evaluation

If you received the Software for the purpose of internal evaluation, as expressed by 3D Incorporated, or if you received the Software without conditions of payment, then the Software is to be used for evaluation purposes only, and this Agreement is effective for a fixed period of time to be determined by 3D Incorporated. If no explicit period of time is given by 3D Incorporated, then this Agreement will terminate in 90 days from receipt of the Evaluation Software, with no written notice of termination required. Upon termination of this agreement, see 9. Term.

3. License Grant

Subject to the terms and conditions of this Agreement, 3D Incorporated grants you a non-exclusive, non-transferable, limited license to: (a) use the copy of the Software and accompanying materials, including a dongle (as applicable to the licensed Software), enclosed in this package (collectively the “Product”) on the Designated System; (b) develop separate software applications derived from the API (the “Applications”); and (c) use, copy, and distribute the Applications; provided, however, that you obtain written approval from 3D Incorporated prior to any sale, license, lease or other distribution of the Applications. You may transfer the Software to the Designated System provided you keep the original Software solely for backup or archival purposes. “Designated Systems” for any Software means a computer system that is: (i) owned or controlled and operated by you; (ii) designated as the computer system on which the Software will be used; and (iii) included a dongle (solely for Software that does not require and unlock code from 3D Incorporated). All rights not expressly granted to you herein are retained by 3D Incorporated. You acknowledge that the Software is copy protected and requires either a key code furnished by 3D Incorporated or an appropriate dongle for continuing operation, as applicable.

4. Software Media and Dongle

You may receive the Product on media which contain various executables or in multiple forms of media. Regardless of the number or types of executables or media you receive, you may use only the media and executables specified in the applicable purchase order or loan agreement. The media may contain executables which have not been licensed; and such unlicensed executables may not be used unless a license is acquired

by you from 3D Incorporated. In the event that a dongle that is included as part of the Product you receive with this Agreement is lost or damaged it cannot be replaced by 3D Incorporated, and such loss or damage will require that you purchase another copy of the Software.

5. Ownership

All rights, title and interest to the Product, and any proprietary information contained on the media, or in the associated materials or dongle, are owned by 3D Incorporated and are protected by copyright, trademark and trade secret law and international treaties. You acquire only the right to use the Product during the term of this Agreement. You agree not to develop separate software applications of any kind derived from the Tools or from any other proprietary information of 3D Incorporated, except for the Applications. Any rights, express or implied, in the Product, and any proprietary information contained in the media or dongle other than those specified in this Agreement are reserved by 3D Incorporated. You must treat the Product like any other copyrighted material except as otherwise provided under this Agreement. You agree not to remove, deface or obscure 3D Incorporated’s copyright or trademark notices or legends, or any other proprietary notices in or on the Product or media.

6. Copies and Modifications

You may make one (1) copy of the Software solely for back-up purpose; provided, however, that you reproduce and include all copyright, trademark, and other proprietary rights notices on the copy. You may not make copies of any of the written documentation included in the Product without prior permission, in writing, from 3D Incorporated. You may not nor may you assist another to modify, translate, convert to another programming language, decompile, reverse engineering or disassemble any portions of the Product. Except as otherwise expressly provided by this Agreement, you may not copy the Software. You agree to notify your employees and agents who may have access to the Product of the restrictions contained in this Agreement and to ensure their compliance with such restrictions.

7. Taxes

You shall be liable for and shall pay all charges and taxes, including all sales and use taxes, which may now or hereafter be imposed or levied upon the license or possession or use of the Product, except taxes based on 3D Incorporated’s income.

8. Confidentiality

By accepting this license, you acknowledge that the Product, and any proprietary information contained in the associated media and dongle, are proprietary in nature to 3D Incorporated and contain valuable trade secrets and other proprietary information developed or acquired at

great expense to 3D Incorporated. You agree not to disclose to others or to utilize such trade secrets or proprietary information except as expressly provided herein.

9. Term

This Agreement is effective from the date you use the Software, until the earlier of: (i) the Agreement is terminated; or (ii) if applicable, the dongle is lost or damaged. 3D Incorporated or you may terminate this Agreement at any time by giving thirty (30) days written notice of termination to the other party. Notwithstanding the above, if you fail to comply with any term of this Agreement, or if you become the subject of a voluntary or involuntary petition in bankruptcy or any proceeding relating to insolvency, receivership, liquidation, or composition for the benefit of creditors, if that petition or proceeding is not dismissed with prejudice within thirty (30) days after filing, 3D Incorporated may terminate this Agreement immediately upon notice to you. Promptly upon termination of this Agreement, you agree to cease all use of the Product, and to either destroy or promptly return to 3D Incorporated the Product, together with all copies you made thereof. Notwithstanding the remedies provided above, 3D Incorporated may enforce all of its other legal rights. Sections 4 – 12 and 14 – 18 will survive termination of this Agreement.

10. Assignment

You may not assign, sublicense, rent, loan, lease, convey or otherwise transfer this Agreement, any applicable unlock code, or the Product without prior written permission from 3D Incorporated. Any unauthorized assignment, sublicense, rental, loan, lease, conveyance or other transfer of any copy of the Product or the unlock code shall be void and shall automatically terminate this Agreement.

11. Limited Warranty

3D Incorporated warrants that the Software provided to you shall operate as described in the accompanying documentation under normal use consistent with the terms of this Agreement, for a period of ninety (90) days from the date of your receipt thereof. For the purposes of this Section 10, "Defective Software" means Software which does not operate as described in the accompanying documentation under normal use during the warranty period. 3D Incorporated's warranty as set forth above shall not be enlarged, diminished or affected by, and no liability shall arise out of, 3D Incorporated's rendering of technical advice or service in connection with the Product. 3D Incorporated does not warrant that the Software will meet your requirement, operate without interruption or be error free. Your sole remedy under this Section 10 shall be, upon return of the Defective Software to 3D Incorporated, at 3D Incorporated's sole discretion: (i) repair or replacement of any Defective Software within the warranty period; or (ii) within the warranty period, return of the amount, if any, paid by you to 3D Incorporated for the Defective Software. Any replacement Software will be warranted for the remainder of the original warranty period or thirty (30) days, whichever is longer.

12. Warranty Exceptions

Except for the warranty expressly provided in Section 10, the Software is provided "as is". To the maximum extent permitted by applicable law, 3D Incorporated disclaims all other warranties of any kind, express or implied, including, but not limited to, implied warranties of performance, merchantability, and fitness for a particular purpose. You bear all risk relating to quality and performance of the Software, and assume the entire cost of all necessary servicing, repair or correction.

Some jurisdictions do not allow limitations on implied warranties, so the above limitation may not apply to you. In that event, such warranties are limited to the warranty period. This warranty gives you specific legal rights. You may also have other rights which vary from jurisdiction to jurisdiction.

13. Limitation of Remedies

3D Incorporated's maximum liability for any claim by you or anyone claiming through or on behalf of you arising out of this Agreement shall not in any event exceed the actual amount paid by you for the license to the Product. To the maximum extent permitted by applicable law, 3D Incorporated shall not be liable for the loss of revenue or profits, expense or inconvenience, or for any other direct, indirect, special, incidental, exemplary or consequential damages, arising out of this Agreement or caused by the use, misuse or inability of use the Product, even if 3D Incorporated has been advised of the possibility of such damages. This limited warranty shall not extend to anyone other than the original user of the Product. Some jurisdictions do not allow the exclusion or limitation of incidental or consequential damages, so the above limitation or exclusion may not apply to you.

14. Support

3D Incorporated is not responsible for maintaining or helping you to use the Product, and is not required to make available to you any updates, fixes or support for the Product (an "Upgrade"), except pursuant to a separate written Software Maintenance Agreement, except that if any license is included by 3D Incorporated with the upgrade which contains terms additional to or inconsistent with this Agreement, then such additional or inconsistent terms shall supersede the applicable portions of this Agreement when applied to the Upgrade.

15. Governing Law

This Agreement shall be governed by the laws of Japan, exclusive of its choice of law principles.

16. General provisions

If any provision of this Agreement is held to be void, invalid, unenforceable or illegal, the other provisions shall continue in full force and effect. Failure of a party to enforce any provision of this Agreement shall not constitute or be construed as a waiver of such provision or of the right to enforce such provision. If any legal action, including arbitration, arises under this Agreement or by any reason of any asserted breach of this Agreement, the

prevailing party shall be entitled to recover all costs and expenses, including reasonable attorneys' fees, incurred as a result of such legal action.

17. Export

You agree to comply fully with all laws and regulations of Japan and other countries ("Export Laws") to assure that the Product is not: (i) exported, directly or indirectly, in violation of Export Laws; or (ii) used for any purpose prohibited by Export Laws.

18. Acknowledgment

This Agreement is the complete and exclusive statement of agreement between the parties and supersedes all proposals or prior agreements, verbal or written, and any other communications between the parties relating to the subject matter of this Agreement. No amendment to this Agreement shall be effective unless signed by an officer of 3D Incorporated.

SmartCollision™ SDK

version 2.01

Copyright

©2007. 3D Incorporated. All rights reserved. Made in JAPAN.

Trademarks

SmartCollision, SmartCollision SDK, are trademarks of 3D Incorporated.
Other brand and product names are trademarks of their respective holders

Web Information

English:

http://www.ddd.co.jp/tech_info/eng_tech_smartcollision.htm

Japanese:

http://www.ddd.co.jp/tech_info/tech_smartcollision.htm

Support

<mailto:haptics@ddd.co.jp>

Corporate Headquarters

3D Incorporated

<http://www.ddd.co.jp/>

Urban Square Yokohama 2F,

1-1 Sakae-cho, Kanagawa-ku, Yokohama, 221-0052, Japan

tel:+81-45-450-1330, fax:+81-45-450-1331

<mailto:haptics@ddd.co.jp>

Contents

1. PREFACE	1-1
2. CLASS INTERFACE	2-1
2.1 THE METHODS OF SCSCENEMANAGER	2-2
2.1.1 <i>SCSceneManager()</i>	2-3
2.1.2 <i>~SCSceneManager()</i>	2-4
2.1.3 <i>SetAttribute()</i>	2-5
2.1.4 <i>GetAttribute()</i>	2-6
2.1.5 <i>AddObject()</i>	2-7
2.1.6 <i>DeleteObject()</i>	2-8
2.1.7 <i>AddObjectToGroup()</i>	2-9
2.1.8 <i>DeleteObjectFromGroup()</i>	2-10
2.1.9 <i>DeleteGroup()</i>	2-11
2.1.10 <i>ResetGroup()</i>	2-12
2.1.11 <i>SetActivity()</i>	2-13
2.1.12 <i>SetTransformation()</i>	2-15
2.1.13 <i>GetTransformation()</i>	2-16
2.1.14 <i>UpdateStatus()</i>	2-17
2.1.15 <i>GetStatus()</i>	2-18
2.1.16 <i>ResetStatus()</i>	2-20
2.2 THE METHODS OF SBJECT	2-21
2.2.1 <i>SObject()</i>	2-22
2.2.2 <i>~SObject()</i>	2-23
2.2.3 <i>AddTriangles()</i>	2-24
2.2.4 <i>SetTransformation()</i>	2-26
2.2.5 <i>GetTransformation()</i>	2-27
APPENDIX A.....	I
APPENDIX A- 1 ATTRIBUTES OF SCSCENEMANAGER	I
APPENDIX A- 2 ACTIVITIES OF MINIMUM DISTANCE COMPUTATION.....	II
APPENDIX A- 3 TYPES OF TRANSFORMATION.....	III
APPENDIX A- 4 TYPES OF STATUS.....	IV

Tables

Table 2-1: Methods of SCSceneManager.....	2-2
Table 2-2: Methods of SCObject.....	2-21
Table A- 1:Attributes of SCSceneManager.....	I
Table A- 2: Activities of collision detection according to the activities of two groups	II
Table A- 3:Types of transformation	III
Table A- 4: Types of status of SCSceneManager	IV

1. Preface

This reference manual describe class interface of SmartCollisionSDK.

2. Class interface

SmartCollisionSDK consists of two classes, namely SCSceneManager, SObject. Class interface of each class is described below.

2.1 The methods of SCSceneManager

The methods of SCSceneManager are as follows.

Table 2-1: Methods of SCSceneManager

Categories	Methods
Constructor	SCSceneManager ()
Destructor	~SCSceneManager ()
Setting/Getting attributes	SetAttribute () GetAttribute ()
Add/Delete object	AddObject() DeleteObject()
Grouping	AddObjectToGroup() DeleteObjectFromGroup() DeleteGroup() ResetGroup()
Setting activity of collision detection	SetActivity()
Setting/Getting transformation	SetTransformation() GetTransformation()
Updating status (Execute collision detection)	UpdateStatus()
Getting status (Getting results of collision detection)	GetStatus()
Resetting status (Resetting results of collision detection)	ResetStatus()

2.1.1 SCSceneManager ()

【Syntax】

SCSceneManager (SCenum mode);

【Description】

The constructor of SCSceneManager.

【Arguments】

⟨INPUT⟩

mode

Sets mode of model data.

Default value is SC_MODE_TRIANGLE_SOUP.

■ SC_SCENE_MANAGER_TRIANGLE_SOUP:

Arbitrary set of triangles or triangle soup.

■ SC_SCENE_MANAGER_CLOSED_POLYHEDRA:

Closed polyhedra. This type is more efficient than SC_MODE_TRIANGLE_SOUP.

⟨OUTPUT⟩

【Return】

2.1.2 ~SCSceneManager ()

【Syntax】

~SCSceneManager (void);

【Description】

The destructor of SCSceneManager.

【Arguments】

【Return】

2.1.3 SetAttribute ()

【Syntax】

```
SCint SetAttributeDouble(SCenum attribute,SCdouble value);  
SCint SetAttributeFloat(SCenum attribute,SCfloat value);  
SCint SetAttributeInteger(SCenum attribute,SCint value);  
SCint SetAttributeEnum(SCenum attribute,SCenum value);
```

【Description】

Sets attributes of SCSceneManager.

【Arguments】

⟨INPUT⟩	
<i>Attribute</i>	Attribute to set. List of attributes are shown in Table A- 1
<i>Value</i>	Value to set.
⟨OUTPUT⟩	

【Return】

- SC_NO_ERROR: There has been no error.
- SC_INVALID_ATTRIBUTE: The attribute to set is invalid.
- SC_INVALID_VALUE: The value to set is invalid.

2.1.4 GetAttribute ()

【Syntax】

```
SCint GetAttributeDouble(SCenum attribute, SCdouble&value);  
SCint GetAttributeFloat(SCenum attribute, SCfloat&value);  
SCint GetAttributeInt(SCenum attribute, SCint&value);  
SCint GetAttributeEnum(SCenum attribute, SCenum&value);  
SCint GetAttributeString(SCenum attribute, const SCchar*&value);
```

【Description】

Gets attributes of SCSceneManager.

【Arguments】

⟨INPUT⟩

Attribute

Attribute to set. List of attributes are shown in Table A- 1

⟨OUTPUT⟩

Value

Value to get.

【Return】

SC_NO_ERROR: There has been no error.

SC_INVALID_ATTRIBUTE: The attribute to get is invalid.

SC_INVALID_VALUE: The value to get is invalid.

2.1.5 AddObject()

【Syntax】

SCint AddObject (SCint id, SObject*object);

【Description】

Adds SObject in the scene. The information of the shape, position and orientation is obtained from SObject. By default, the objects are automatically added to the static group.

【Arguments】

⟨INPUT⟩

id

The ID to set to the object. The value of ID is chosen by the user and must be a positive integer.

object

The address of SObject to add.

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_DUPLICATE_ID: The *id* specified has already been registered.

SC_ERROR_INVALID_TYPE_COMBINATION: The type of SObject does not match the type of SSceneManager.

SC_ERROR_NO_GEOMETRY: The object has no geometry.

SC_ERROR_INVALID_LICENSE: The license is invalid.

SC_ERROR_BAD_ALLOCATION: Bad allocation has happened during the execution.

SC_ERROR_RUNTIME: Runtime error has happened during the execution.

2.1.6 DeleteObject()

【Syntax】

SCint DeleteObject (SCint id);

【Description】

Deletes the object in the scene. The object specified by *id* must have been registered by AddObject.

【Arguments】

⟨INPUT⟩

id

The ID of the object to be deleted.

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_ID: The *id* specified is invalid.

2.1.7 AddObjectToGroup()

【Syntax】

SCint AddObjectToGroup(SCint gid, SCint id);

SCint AddControlledObject(SCint id, SCint gid=SC_DEFAULT_GROUP_ID);

【Description】

Adds the object specified by *id* to the group specified by *gid*. The object specified by *id* must have been registered by AddObject. If the group specified by *gid* does not exist, the new group is created.

A group of objects is treated as one object. The center of rotation of the object which is added first to the group is adopted as the center of rotation of the the group.

AddControlledObject is the obsolete form of AddObjectToGroup.

【Arguments】

〈INPUT〉

id

ID of the object to be added to the group.

gid

ID of the group to be added to.

SC_STATIC_GROUP_ID is a negative integer and is reserved as the static group. SC_STATIC_GROUP_ID must not be specified for *gid*.

〈OUTPUT〉

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_ID: The *id* specified is invalid.

SC_ERROR_INVALID_GROUP_ID: The *gid* specified is invalid.

2.1.8 DeleteObjectFromGroup()

【Syntax】

```
SCint DeleteObjectFromGroup(SCint gid,SCint id);  
SCint DeleteControlledObject (SCint id, SCint gid=SC_DEFAULT_GROUP_ID);
```

【Description】

Deletes the object specified by *id* from the group. The object specified by *id* must have been registered by `AddObject` and added to the group by `AddObjectToGroup`. Objects deleted from their groups are automatically returned to the static group.

`DeleteControlledObject` is the obsolete form of `DeleteObjectToGroup`.

【Arguments】

⟨INPUT⟩

id

ID of the object to be deleted from the group.

gid

ID of the group to be deleted from.

`SC_STATIC_GROUP_ID` is a negative integer and is reserved as the static group. `SC_STATIC_GROUP_ID` must not be specified for *gid*.

⟨OUTPUT⟩

【Return】

`SC_NO_ERROR`: There has been no error.

`SC_ERROR_INVALID_ID`: The *id* specified is invalid.

`SC_ERROR_INVALID_GROUP_ID`: The *gid* specified is invalid.

2.1.9 DeleteGroup()

【Syntax】

SCint DeleteGroup(SCint gid);

【Description】

Deletes a group specified by *gid*.

【Arguments】

〈INPUT〉

gid

ID of the group to be deleted.

SC_STATIC_GROUP_ID is a negative integer and is reserved as the static group. SC_STATIC_GROUP_ID must not be specified for *gid*.

〈OUTPUT〉

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_GROUP_ID: The *gid* specified is invalid.

2.1.10 ResetGroup()

【Syntax】

SCint ResetGroup(void);

【Description】

Deletes all existing groups and adds all objects to the static group whose *gid* is SC_STATIC_GROUP_ID.

【Arguments】

⟨INPUT⟩

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

2.1.11 SetActivity()

【Syntax】

SCint SetActivityGroup (SCint gid,SCenum type);
SCint SetActivityGroupPair (SCint gid1,SCint gid2, SCenum type);
SCint SetActivityObject (SCint oid,SCenum type);
SCint ActivateObject (SCint oid);
SCint DeactivateObject (SCint oid);

【Description】

Sets activity of the object, the group or the pair of groups specified by ID or IDs.

ActivateObject and DeactivateObject are the obsolete forms of SetActivity.

ActivateObject(oid) is equivalent to SetActivityObject (oid , SC_ACTIVITY_ACTIVE).

DeactivateObject(oid) is equivalent to SetActivityObject (oid , SC_ACTIVITY_INACTIVE).

【Arguments】

〈INPUT〉

oid

The ID of the object to set activity of.

gid

The ID of the group to set activity of.

gid1,gid2

The IDs of the pair of groups to set activity of.

type

Possible types of activities are as follows.

■ SC_ACTIVITY_ACTIVE: The object, the group or the pair of groups is taken into account of collision detection.

■ SC_ACTIVITY_INACTIVE: The object, the group or the pair of groups is not taken into account of collision detection. Statuses of collision detection are discarded.

■ SC_ACTIVITY_PASSIVE: The group is taken into account of collision detection only if the other group is active. The penetration depth computation is performed only in the direction from the active group to the passive group.

■ SC_ACTIVITY_SLEEPING: The group is taken into account of collision detection only if the other group is active. However, statuses of collision detection are kept in memory, even if the other group is passive.

■ SC_ACTIVITY_ONE_WAY_ACTIVE: The collision detection from *gid1* to *gid2* is performed, ignoring the other configurations.

■ SC_ACTIVITY_ONE_WAY_INACTIVE: The collision detection from *gid1* to *gid2* is not performed, ignoring the other configurations.

Activities of collision detection according to the activities of two groups are shown in Appendix A- 2.

〈OUTPUT〉

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_TYPE: The type specified is invalid.

SC_ERROR_INVALID_ID: The *id* specified is invalid.

SC_ERROR_INVALID_GROUP_ID: The *gid* specified is invalid.

2.1.12 SetTransformation()

【Syntax】

```
SCint SetTransformation(SCint gid, SCenum type, const Float*trans);  
SCint SetTransformation(SCint gid, SCenum type, const SCdouble*trans);  
SCint SetTransformation(SCenum type, const Float*trans, SCint gid=0);  
SCint SetTransformation(SCenum type, const SCdouble*trans, SCint gid=0);
```

【Description】

Sets transformation of the group specified by *gid*.

【Arguments】

⟨INPUT⟩

gid

ID of a group. SC_STATIC_GROUP_ID is a negative integer and is reserved as static object group.

ID of the group to be set transformation of.

SC_STATIC_GROUP_ID is a negative integer and is reserved as the static group. SC_STATIC_GROUP_ID must not be specified for *gid*.

trans

Transformation to set

type

The type of transformation. Possible types of transformation are shown in Appendix A- 3.

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_TYPE: The type specified is invalid.

SC_ERROR_INVALID_GROUP_ID: The *gid* specified is invalid.

2.1.13 GetTransformation()

【Syntax】

```
SCint GetTransformation(SCint gid ,SCenum type,SCdouble position[3]) const;  
SCint GetTransformation(SCenum type,SCfloat position[3], SCint gid=0) const;
```

【Description】

Gets transformation of the group specified by *gid*.

【Arguments】

⟨INPUT⟩

gid

ID of a group. SC_STATIC_GROUP_ID is a negative integer and is reserved as static object group.

type

The type of transformation. Possible types of transformation are shown in Appendix A- 3.

⟨OUTPUT⟩

position

Position to get

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_TYPE: The type specified is invalid.

SC_INVALID_ID: The ID specified is invalid.

SC_ERROR_INVALID_GROUP_ID: The *gid* specified is invalid.

2.1.14 UpdateStatus()

【Syntax】

SCint UpdateStatus(void);

【Description】

Updates the statuses of distance computation or penetration depth computation with respect to current transformations.

【Arguments】

⟨INPUT⟩

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: If there is no error, otherwise as follows.

SC_ERROR_INVALID_INITIAL_TRANSFORMATION: Failed to perform penetration depth computation. To perform the penetration depth computation, non-penetrating initial transformation of the controlled object is required.

SC_ERROR_UNKNOWN_DISTANCE: The controlled object is not penetrating with the static object, but the result of distance computation is unknown. This happens when the minimum distance between the controlled object and the static objects is further than threshold of distance computation.

SC_ERROR_NO_RESULT: There is no result.

SC_ERROR_FAILED: Failed to get status.

SC_ERROR_BAD_ALLOCATION: Bad allocation has happened during the execution.

SC_ERROR_RUNTIME: Runtime error has happened during the execution.

2.1.15 GetStatus()

【Syntax】

```
SCint GetStatus(SCenum type, SCint*status);
SCint GetStatus(SCenum type, SCfloat*status);
SCint GetStatus(SCenum type, SCdouble*status);
SCint GetStatus(SCenum type, SCint*status, SCint index, SCbool reverseFlag=false);
SCint  GetStatus(SCenum  type, SCfloat*status,  SCint  index,  SCbool
reverseFlag=false);
SCint  GetStatus(SCenum  type, SCdouble*status,  SCint  index,  SCbool
reverseFlag=false);
```

【Description】

Gets the statuses of minimum distance/penetration depth computation between groups of objects. If there are more than two groups of objects, the number of statuses is at most the number of combination of the two groups. Only the statues between the two groups whose distance is within less equal than SC_MAX_DISTANCE can be obtained. The number of statues can be obtained by using SC_STATUS_COUNT. If the reverseFlag is true, the status reversed the order of the groups can be obtained.

【Arguments】

⟨INPUT⟩

index

Index specifies one of the results. Index starts at 0.

reverseFlag

If the reverseFlag is true, the status reversed the order of the groups can be obtained.

type

Type of status to get. Possible types of status are shown in Appendix A- 4.

⟨OUTPUT⟩

status

Status to get.

【Return】

SC_NO_ERROR: There has been no error. Distance computation or penetration depth computation has been performed normally.

SC_ERROR_INVALID_INITIAL_TRANSFORMATION: Failed to perform penetration depth computation. To perform the penetration depth computation, non-penetrating initial transformation of the controlled object is required.

SC_ERROR_UNKNOWN_DISTANCE: the controlled object is not penetrating with the static object, but the result of distance computation is unknown. This happens when the minimum distance between the controlled object and the static objects is further than threshold of distance computation.

SC_ERROR_NO_RESULT: There is no result.

SC_ERROR_INVALID_TYPE: The type specified is invalid.

SC_ERROR_INVALID_INDEX: The index specified is invalid.

SC_ERROR_FAILED: Failed to get status.

2.1.16 ResetStatus()

【Syntax】

SCint ResetStatus(void);

【Description】

Resets the statuses of distance computation or penetration depth computation.

【Arguments】

⟨INPUT⟩

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

2.2 The methods of SObject

The methods of SObject are as follows.

Table 2-2: Methods of SObject

Categories	Methods
Constructor	SObject ()
Destructor	~SObject ()
Setting geometry	AddTriangles()
Setting/Getting transformation	SetTransformation() GetTransformation()

2.2.1 SObject ()

【Syntax】

```
SObject (SCenum type);  
SObject (void);
```

【Description】

The constructor of SObject.

【Arguments】

⟨INPUT⟩

type

Type of triangles to set.

■ SC_OBJECT_TYPE_CLOSED_POLYHEDRA / SC_OBJECT_TYPE_CLOSED_POLYHEDRON: Closed polyhedra. This type of object can be add to SSceneManager in SC_MODE_CLOSED_POLYHEDRA mode.

■ SC_OBJECT_TYPE_TRIANGLE_SOUP: Arbitrary set of triangles. So-called triangle soup. This type of object can be add to SSceneManager in SC_MODE_TRIANGLE_SOUP mode.

⟨OUTPUT⟩

【Return】

2.2.2 ~SCObject ()

【Syntax】

~SCObject (void);

【Description】

The distructor of SCObject.

【Arguments】

【Return】

2.2.3 AddTriangles()

【Syntax】

SCint AddTriangles (const SCfloat*vertices, SCint vertexNum, const SCint triangles, SCint triangleNum, const SCchar*bvhFile=NULL);

SCint AddTriangles (const SCdouble*vertices, SCint vertexNum, const SCint triangles, SCint triangleNum, const SCchar*bvhFile=NULL);

SCint AddTriangles (SCenum type, const SCfloat*vertices, SCint vertexNum, const SCint triangles, SCint triangleNum, const SCchar*bvhFile=NULL);

SCint AddTriangles (SCenum type, const SCdouble*vertices, SCint vertexNum, const SCint triangles, SCint triangleNum, const SCchar*bvhFile=NULL);

【Description】

Adds triangles to the object.

It is possible to call AddTriangles at multiple times, but combinations of different type of model are not allowed.

【Arguments】

⟨INPUT⟩

type

Type of triangles to set.

■ SC_OBJECT_TYPE_CLOSED_POLYHEDRA / SC_OBJECT_TYPE_CLOSED_POLYHEDRON: Closed polyhedra. This type of object can be add to SCSceneManager in SC_MODE_CLOSED_POLYHEDRA mode.

■ SC_OBJECT_TYPE_TRIANGLE_SOUP: Arbitrary set of triangles. So-called triangle soup. This type of object can be add to SCSceneManager in SC_MODE_TRIANGLE_SOUP mode.

vertices

The array of vertices. The array has the 3*vertexNum elements.

vertexNum

The number of vertices.

triangles

The array of index of vertices of triangles. Index starts from 0. The array has the 3*triangleNum elements.

triangleNum

The number of triangles.

bvhFile

File name of BVH file to set, if the type of triangles is SC_OBJECT_TYPE_CLOSED_POLYHEDRA. Otherwise, ignores this argument. If BVH file exists, reads the file. If BVH file does not exist, creates the file. If BVH file is NULL or not specified, creates a temporary BVH when the object is added in the scene.

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_INVALID_TYPE: The type specified is invalid.

SC_ERROR_FAILED: Failed to execution.

SC_ERROR_INVALID_TYPE_COMBINATION: The combination of type of data is invalid.

SC_ERROR_INVALID_DATA: The data specified is invalid.

SC_ERROR_INVALID_BVH_FILE: The BVH file specified is invalid.

SC_ERROR_INVALID_LICENSE: The license is invalid.

SC_ERROR_BAD_ALLOCATION: Bad allocation has happened during the execution.

SC_ERROR_RUNTIME: Runtime error has happened during the execution.

2.2.4 SetTransformation()

【Syntax】

```
SCint SetTransformation(SCenum type,const SCfloat*transformation);  
SCint SetTransformation(SCenum type,const SCdouble*transformation);
```

【Description】

Sets position of the object. After a SCObject has been added to SCSceneManager, it is required that you use the method SCSceneManager::SetTransformation to set the transformations of the SCObject.

【Arguments】

⟨INPUT⟩

transformation

type

Transformation to set.

The type of transformation. Possible types of transformation are shown in Appendix A- 3.

⟨OUTPUT⟩

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_FAILED: Failed to execution.

2.2.5 GetTransformation()

【Syntax】

```
SCint GetTransformation(SCenum type,SCfloat position[3]) const;  
SCint GetTransformation(SCenum type,SCdouble position[3]) const;
```

【Description】

Gets position of the object. Even after a SObject has been added to SCSceneManager, it is possible to use SObject::GetTransformation to get transformations for each object.

【Arguments】

⟨INPUT⟩

type

The type of transformation. Possible types of transformation are shown in Appendix A- 3.

⟨OUTPUT⟩

transformation

Transformation to get

【Return】

SC_NO_ERROR: There has been no error.

SC_ERROR_FAILED: Failed to execution.

Appendix A

Appendix A- 1 Attributes of SCSceneManager

Table A- 1 shows attributes of SCSceneManager.

Table A- 1:Attributes of SCSceneManager

Name of attributes	Type	Units	Description
SC_SCENE_MANAGER_TOLERANCE	SCdouble SCfloat	[Length]	Tolerance for penetration depth computation. Default value is 0.2.
SC_SCENE_MANAGER_ROTATION_MODE	SCenum		Rotation mode. ■ SC_ROTATION_MODE_NONE: Contact orientation keeps the value at the time when the penetration happened. This is the default. ■ SC_ROTATION_MODE_INPUT: The combination of the penetration depth vector and the penetration rotation vector is determined such that the norm of the penetration rotation vector has the minimum value. ■ SC_ROTATION_MODE_FREE: The combination of the penetration depth vector and the penetration rotation vector is determined such that the norm of the penetration depth has the minimum value. ■ SC_ROTATION_MODE_MIX: The combination of the penetration depth vector and the penetration rotation vector is determined such that potential has the minimum value.
SC_SCENE_MANAGER_MAX_ITERATION	SCint		Maximum iteration of penetration depth computation. Default value is 5.
SC_SCENE_MANAGER_MAX_DISTANCE	SCdouble SCfloat	[Length]	Maximum distance for distance computation. If the distance between the controlled object and the static object beyond the value, the results of distance computation may be unknown. Default value is 0.5.
SC_SCENE_MANAGER_FORCE_STIFFNESS	SCdouble SCfloat	[Force/Length]	Stiffness of force to calculate potential. Default value is 0.4.
SC_SCENE_MANAGER_TORQUE_STIFFNESS	SCdouble SCfloat	[Force*Length]	Stiffness of torque to calculate potential. Default value is 100.
SC_SCENE_MANAGER_SAFETY_COEFFICIENT	SCdouble SCfloat		Safety coefficient of penetration depth computation. The value must be larger than 0 and less than 0.5. Default value is 0.49.
SC_SCENE_MANAGER_PENETRATION_DEPTH_COMPUTATION	SCenum		Execution of penetration depth computation. ■ SC_TRUE: Penetration depth computation is enabled. This is the default. ■ SC_FALSE: Penetration depth computation is disabled.
SC_VERSION	const SCchar*		Version of SmartCollision.

Appendix A- 2 Activities of minimum distance computation

Table A- 2 shows activities of collision detection according to the activities of two groups. In Table A- 2 , the group at the origin of the arrow plays the role of the **target**, and the group at the head of the arrow plays the role of the **opponent**.

Table A- 2: Activities of collision detection according to the activities of two groups

Activity of group A \ Activity of group B	SC_ACTIVITY_ACTIVE	SC_ACTIVITY_SLEEPING	SC_ACTIVITY_PASSIVE	SC_ACTIVITY_INACTIVE
SC_ACTIVITY_ACTIVE	$A \rightleftharpoons B$	$A \rightarrow B$	$A \rightarrow B$	—
SC_ACTIVITY_SLEEPING	$A \leftarrow B$	—	—	—
SC_ACTIVITY_PASSIVE	$A \leftarrow B$	—	—	—
SC_ACTIVITY_INACTIVE	—	—	—	—

Appendix A- 3 Types of transformation

Table A- 3 shows types of transformation.

Table A- 3:Types of transformation

Type of transformation	Type of array	Size	Description
SC_POSITION_ORIGIN	SCfloat SCdouble	3	The origin of local coordinates system of the object in world coordinates system.
SC_POSITION_WORLD_CENTER	SCfloat SCdouble	3	The center of rotation of the object in world coordinates system.
SC_POSITION_LOCAL_CENTER	SCfloat SCdouble	3	The center of rotation of the object in local coordinates system.
SC_ORIENTATION_QUATERNION	SCfloat SCdouble	4	The orientation of the object specified by quaternion.
SC_ORIENTATION_MATRIX	SCfloat SCdouble	16	The orientation of the object specified by matrix. Transformation is expressed by 4x4 matrix.
SC_TRANSFORMATION_MATRIX	SCfloat SCdouble	16	Transformation of the object specityed by 4x4 matrix.
SC_POSITION_NEW_WORLD_CENTER	SCfloat SCdouble	3	The new center of rotation of the object in world coordinates system.
SC_POSITION_NEW_LOCAL_CENTER	SCfloat SCdouble	3	The new center of rotation of the object in local coordinates system.

Appendix A- 4 Types of status

Table A- 4 shows types of status of SCSceneManager.

Table A- 4: Types of status of SCSceneManager

Type of transformation	Type of array	Size	Description
SC_PAIR_COUNT SC_STATUS_COUNT	SCint	1	The number of pair.
SC_STATUS_RESULT	SCint	1	The status of result. The possible values are as follows. <ul style="list-style-type: none"> ■ SC_NO_ERROR: Either minimum distance computation or penetration depth computation was executed normally. ■ SC_ERROR_INVALID_INITIAL_TRANSFORMATION : There were intersections, before penetration depth computation started. ■ SC_ERROR_UNKNOWN_DISTANCE: There was no penetration, but minimum distance computation was not executed, because the distance was greater than the threshold. ■ SC_ERROR_NO_RESULT: There was no result between the pair in this direction.
SC_GROUP_ID	SCint	2	The IDs of the pair of the groups, which have end points of minimum distance / penetration depth computation.
SC_OBJECT_ID	SCint	2	The IDs of the pair of the objects, which have end points of minimum distance /penetration depth computation.
SC_TARGET_OBJECT_ID SC_CONTROLLED_OBJECT_ID	SCint	1	The ID of the target object, which has the end point of distance/penetration depth computation.
SC_OPPONENT_OBJECT_ID SC_STATIC_OBJECT_ID	SCint	1	The ID of the opponent object which has the end point of distance/penetration depth computation.
SC_DISTANCE	SCfloat SCdouble	1	Positive value means the minimum distance between the pair. If the value is zero or negative, there is penetration between the pair. If penetration depth computation is enabled, the magnitude means magnitude of translational penetration depth vector. Otherwise, the magnitude has no meaning.
SC_CONTACT_NORMAL	SCfloat SCdouble	3	The normal between the target in contact state and opponent
SC_MD_VECTOR	SCfloat SCdouble	3	Minimum distance vector. If there are penetrations, this is zero vector.
SC_TPD_VECTOR	SCfloat SCdouble	3	Translational penetration depth vector. If there is no penetration, this is zero vector.
SC_RPD_VECTOR	SCfloat SCdouble	3	Rotational penetration depth vector. If there is no penetration, this is zero vector.
SC_RPD_QUATERNION	SCfloat SCdouble	4	Quaternion representation of rotational penetration depth vector. If there is no penetration, this is identical quaternion.
SC_PD_MATRIX	SCfloat SCdouble	16	Matrix representation of penetration depth.
SC_PD_INVERSE_MATRIX	SCfloat SCdouble	16	Inverse matrix of penetration depth.
SC_CONTACT_POSITION	SCfloat SCdouble	3	The contact position. The position is expressed by the center of rotation of the object in world coordinates system.
SC_CONTACT_ORIENTATION	SCfloat SCdouble	4	The contact orientation. The orientation is expressed by quaternion representation.

SC_CONTACT_TRANSFORMATION_MATRIX	SCfloat SCdouble	16	Contact transformation. Transformation is specified by 4x4 matrix.
SC_POINT_ON_TARGET SC_POINT_ON_CONTROLLED_OBJECT	SCfloat SCdouble	3	The end point on the target of the result of minimum distance/penetration depth computation.
SC_POINT_ON_TARGET_IN_CONTACT SC_POINT_ON_CONTACT_OBJECT	SCfloat SCdouble	3	The end point on the target in contact of the result of penetration depth computation.
SC_POINT_ON_OPPONENT SC_POINT_ON_STATIC_OBJECT	SCfloat SCdouble	3	The end point on the opponent of the result of distance/penetration depth computation.